

ATMS CORE 1.8.6 changes

The new release of the ATMS CORE software was developed in October 2021. The following functions have been provided in the software for the various innovations, further development and bug fixing:

Innovations:


- Implementation and support of the new software package "ATMS CORE Mobile"

ATMS CORE Mobile

Enables item searches and shopping carts to be filled using mobile devices. The application runs in the browser and does not have to be installed as an app. This works across platforms on all devices that have browser support with current web browsers. At the moment the application is only available in German.


To start the application, follow the link on the Toolbase website.

The application is automatically installed in the browser. We recommend adding the application to your favorites in order to speed up the loading of the application in the future.



Update Information


After the installation, the login screen for connecting to one or more ATMS CORE systems is displayed.



The screenshot shows a mobile application interface for ATMScore. At the top, there is a red header bar containing the ATMScore logo on the left and a settings gear icon on the right. Below the header, the login form consists of three input fields: 'Passwort:' (password), 'PIN:', and 'System:'. The 'System:' field is a dropdown menu. A red 'Login' button is positioned below the input fields. At the bottom of the screen, the 'TOOLBASE' logo is displayed.


In order to connect to a system, the mobile device must be in the same network segment as the ATMS CORE software.

Click on the settings symbol in the top right to get to the system settings.




Update Information

All systems that have already been stored are displayed in the settings area. In order to connect to a system on the login page, it must be created here.



To create a new system you have to click on the plus symbol at the top right which takes you to the input mask for the connection information to an ATMS CORE system.




Update Information

The following data is required in the system setup:
the IP address of the target system,
a self-assigned system name,
the type of connection installed on the target system (http or https).

If this data is not available, please contact your IT department.

After entering the data, "Add" must be clicked.

< Systemeinrichtung 


IP-Adresse:

Systembezeichnung:

HTTP-Verbindung verwenden

Update Information

The new system is displayed in the list of systems. Several systems can be stored at the same time. There is no check as to whether the data entered are correct. The system is only searched for in the network on the login page.




It is possible to edit or delete the entries using the two buttons on the right.




Update Information

With Back, you get to the login screen. Here, under the item System, all systems with which a connection could be established are displayed. If a system is not displayed, it is currently not accessible from the mobile device.

The display text of the system is structured as follows: Unique system designation from the location of the system followed by a hyphen and the system designation chosen by the user when the system was created. If several systems are installed under one IP address (ATMS CORE Cloud or Server) several entries are offered for selection.




The screenshot shows the Toolbase login interface. At the top, there is a red triangle logo and a plus sign. Below this, there are three input fields: 'Passwort:' (password), 'PIN:', and 'System:'. The 'System:' field is a dropdown menu currently showing 'Toolbase 1113 - Mobile'. Below the input fields is a red 'Login' button. At the bottom of the screen, the Toolbase logo is displayed.



This close-up shows the 'System:' dropdown menu. The dropdown is open, displaying three options: 'Toolbase 1113 - Mobile' (highlighted in red), 'Toolbase 1113 - Mobile', and 'Toolbase 1112 - Mobile'. The other two options are in white text on a light gray background.

Update Information

To log into a system, the same password / PIN combination is used as on the system itself. Enter this and confirm this with "Login".



The screenshot shows a mobile application interface for logging into a system. At the top, there is a red triangular logo and a plus sign. Below this, there are three input fields: "Passwort:" with a masked password field, "PIN:" with a masked PIN field, and "System:" with a dropdown menu showing "Toolbase 1112 - Mobile". A red "Login" button is positioned below the input fields. At the bottom of the screen, the "TOOLBASE" logo is displayed.

Update Information


After logging in, you come to the main menu. Depending on the rights assigned to the system, you can see different processes. In order to fill the shopping cart, the user must also have the right to use the shopping cart function on the system. Otherwise, the user can only view article data without preparing a removal.

Example:


Users only with withdrawal rights:



Users with withdrawal rights and shopping cart:




The further processes depend on the settings on the main system. When the article search is activated, the product group tree opens, if it is activated. Here, product group user filters are taken into account.




Update Information

With the selection of the main product group, the next sub-group is then displayed. Here, product group user filters are taken into account.




At the end you get to the article selection. There, all articles are listed with article number and article name according to the previous selection.




Update Information

The list of articles can be restricted using the search field.




The filter symbol to the right of the search field can be used to set which master data is to be taken into account for the search. This is stored in the application with Save.




Update Information

By tapping on the article in the list, it can be selected. The article view is opened and the article master data with the stored Image 1 is displayed.




Update Information

Tapping the shopping cart symbol at the top right of the list opens the input mask for the withdrawal data.



The screenshot shows the article input mask for a drill bit. At the top left, there is a back arrow and the text 'Artikel'. At the top right, there is a red shopping cart icon. Below the header, on the left, is an image of a yellow and blue drill bit. To the right of the image, the following information is displayed: 'Artikelnummer: 142895 20', 'Artikelname: Gewindebohrer M20 Durchgang TiN', and 'Auf Lager: 25'. Below this information, there is a 'Menge:' label followed by a numeric input field containing the value '0'. Underneath the quantity field is a 'Kostenstelle I:' label followed by a dropdown menu with the text 'Kostenstelle auswählen...'. At the bottom of the form is a red button labeled 'Hinzufügen'.


The first thing you can do here is enter the desired withdrawal quantity.




This screenshot is identical to the one above, but the 'Menge:' input field, which now contains the value '1', is circled in red to highlight the action of entering a quantity.

Update Information

If the Cost Center query is switched on in the system, Cost Center 1 can also be entered here. At the moment only one cost center can be queried as a list.



Artikel


 Artikelnummer: 142895 20
Artikelname: Gewindebohrer
M20
Durchgang TiN
Auf Lager: 25

Menge:


Kostenstelle I:
Kostenstelle auswählen...
Kostenstelle I
Kostenstelle II
Kostenstelle III
Kostenstelle IV
Kostenstelle V

javascript:

After the entry, the article is displayed with the entered values for verification. The values can be edited again or the withdrawal preparation can be completed by clicking on "Add".



Artikel

 Artikelnummer: 142895 20
Artikelname: Gewindebohrer
M20
Durchgang TiN
Auf Lager: 25


Menge:

Kostenstelle I:

Hinzufügen

Update Information

The article is placed in the shopping cart and this is automatically opened for checking.



The entry can be edited or deleted using the two buttons on the right.



Update Information

The Back button at the top left takes you to the main menu, where you can select additional articles using the article search or to log off.

You can unsubscribe using the unsubscribe button at the top right.

You can also call up the shopping cart there again to edit it.



Additional QR code function in the shopping cart:

There is a QR code symbol in the shopping cart at the top right. This can be used to call up a scannable QR code.





Update Information

This QR code contains the login data for the source system.
If this is equipped with a corresponding 2D barcode scanner, you can scan the code to log in directly to the system and start the withdrawal from the shopping cart.


The QR code can be shared.

This function can be used to carry out withdrawals by people who do not have access to a system by default.



Further development:

- Extension of the language selection by a new language "Croatian". If you want to use it, it can be activated after the update via a "License RENEWAL". All systems delivered from October 2021 have automatically activated the new language.



The screenshot shows the TOOLBASE website header with the logo on the left and navigation icons (Admin Kunde, Language, Log off) on the right. Below the header is a 'Language selection' dropdown menu. The menu is open, showing a list of languages. The 'hrvatski (Hrvatska) (Croatian (Croatia))' option is circled in red. Other visible options include Deutsch (Deutschland) (German (Germany)), English (United States) (English (United States)), Nederlands (Nederland) (Dutch (Netherlands)), français (France) (French (France)), italiano (Italia) (Italian (Italy)), and polski (Polska) (Polish (Poland)).

Language Selection
Deutsch (Deutschland) (German (Germany))
English (United States) (English (United States))
hrvatski (Hrvatska) (Croatian (Croatia))
Nederlands (Nederland) (Dutch (Netherlands))
français (France) (French (France))
italiano (Italia) (Italian (Italy))
polski (Polska) (Polish (Poland))




The screenshot shows the TOOLBASE website header with the logo on the left and navigation icons (Admin Kunde, Korзина za kupovinu, Pomoć, Favoriti, Jezik, Ocjena) on the right. Below the header is a navigation menu on the left with items: Oduzimanje, Storniranje, Punjenje, Žurnali i popisi, Analiza, and Administracija. The main content area is titled 'Artikl' and contains the text 'Oduzimanje artikla ili alata za zajam'.

Navigation	Main Content
Oduzimanje	Artikl
Storniranje	Oduzimanje artikla ili alata za zajam
Punjenje	
Žurnali i popisi	
Analiza	
Administracija	

Update Information

- Extension of the display of the item price by a uniform currency symbol. This can be stored in the location area. It is used to improve the view of prices. Price fields for withdrawal and filling are automatically supplemented by the currency symbol stored in the location.


Storing the desired uniform currency symbol in the location:



Location	
Location number	1
Location	Toolbase
Unique system name	Toolbase 1112
ATMS LEARN	
Client number	1112
Light keyboard visible	<input type="checkbox"/>
Alias name	Toolbase 1112
Calculation period	10
Show user image	<input type="checkbox"/>
Show user name	<input type="checkbox"/>
Show price	<input type="checkbox"/>
Show maximum inventory	<input type="checkbox"/>
Item title	Name of item
Item description	Item number
Item description 1	Item number supplier
Item description 2	Item 2
Supplier item title	Item number supplier
Supplier item description	Name of item
Supplier item description 1	Item number
Supplier item description 2	Item 2
Order inactive items	<input type="checkbox"/>
Session timeout in seconds	180
Light top bar	Expanding
Default withdrawal quantity	0
Show scrollbar	<input type="checkbox"/>
Fixed favourites management	<input type="checkbox"/>
Number of favourites	All
Show all items in item selection	<input type="checkbox"/>
View item stock individually	<input type="checkbox"/>
Activate zoom function	<input type="checkbox"/>
Tool file view	<input type="checkbox"/>
Currency symbol	€

Default withdrawal quantity	0
Show scrollbar	<input type="checkbox"/>
Fixed favourites management	<input checked="" type="checkbox"/>
Number of favourites	All
Show all items in item selection	<input type="checkbox"/>
View item stock individually	<input type="checkbox"/>
Activate zoom function	<input type="checkbox"/>
Tool file view	<input type="checkbox"/>
Currency symbol	€

Item view in the withdrawal / filling process including price with currency symbol:



TOOLBASE


Admin Kunde Help Favourites Language Log off

Kniehebel Item withdrawal: Item selection Withdrawal

Item number: 256002
Item number supplier: 256002-L
Name of item: Kniehebel
Term 2: 11,70 g
Term 3: Verbrauchsartikel
Bar code: 465746533
Price: 11,50 €
Inventory: 9
Dimension: 3,0
Colour code: schwarz
Tool condition: All


Number: 0

Immediate withdrawal Into the shopping basket



Toolbase®


Edit Information



TOOLBASE


Kniehebel Item withdrawal: Item selection Withdrawal

Item number: 256002
Item number supplier: 256002-L
Name of item: Kniehebel
Term 2: 11,70 g
Term 3: Verbrauchsartikel
Bar code: 465746533
Price: 11,50 €
Inventory: 9
Dimension: 3,0
Colour code: schwarz
Tool condition: All



Update Information

- Extension of e-mail dispatch to include support for TLS 1.2 and TLS 1.3. In order to use these protocols, the checkbox "Use new implementation" must be checked in the location under the tab "E-mail address".



The screenshot shows the 'Location' configuration page in the Toolbase administration system. The 'E-mail address' tab is selected, and the 'Use new implementation' checkbox is checked. A red circle highlights this checkbox and the 'Encryption' dropdown menu.

Report	Import / Export	Printer management
SMTP Server	smtp.toolbase.de	
E-Mail reply address	E-MAIL@Toolbase.de	
User name	User@Toolbase.de	
Old password	*****	
New password		
Port	465	
Encryption	TLS	
Use new implementation	<input checked="" type="checkbox"/>	
Check SMTP connection every 5 minutes	<input type="checkbox"/>	

Bugfixing:

- Fixed the problem that instruction documents could no longer be created
- Fixed the problem that with ATMS CORE Server / Cloud parts lists were displayed although they were not assigned to the location.
- Fixed the problem that the import of user groups led to NULL entries in the database when importing / exporting customer data.
- Fixed the problem that no levels were displayed in the inventory control for the Toolbase AR-18L dispenser type.
- Fixed the problem of incorrect stock displays during correction postings in stock control.
- Fixed the problem that reports were no longer displayed in the main menu if all journals were deactivated.
- Fixed the problem that in certain cases it was not possible to save the compartments visualization. The newly created compartments were not displayed in the drawer.
- Fixed the problem that accessory articles were not displayed when the article was removed.
- Revision of the translation file. Fixed various text and translation errors.